

www.UUDynamics.com



iSTAR Remote Access / UUStation

操作手冊

群浩科技股份有限公司

110台北市信義區忠孝東路五段508號7樓之1 TEL: 02-27278080 FAX: 02-27275544
7F-1, No.508, Sec. 5, Zhongxiao E. Rd., Xinyi Dist., Taipei City 110, Taiwan (R.O.C.) TEL: +886-2-27278080 TEL: +886-2-27275544

Copyright©2010 UUDynamics Inc. All rights reserved. UUDynamics UUDynamics logo are registered trademarks of UUDynamics Inc.
All other brands, product names, or trademarks mentioned are the property of their respective owners. All specifications are subject to change without notice.

目錄

iSTAR Remote Access安裝設定

- 1. 設定IP 2
- 2. 取得IP 4

UUStation 設定

- 1. UUStation安裝..... 5
- 2. 編輯user1 5
- 3. 執行user1 6

iSTAR Remote Access 安裝設定


1. 設定IP

1 點選「發布應用」

2 選擇「iSTAR Remote Access」按「編輯」



在「IP/子網域」中填入內網的IP網域。




選擇使用者




2. 取得IP

設定完成後，重新登入會看到「iSTAR Remote Access」圖示




雙擊「iSTAR Remote Access」圖示後，跳出「遠端連線狀態」視窗，可看到一IP地址即表示設定完成



UUStation 安裝設定


1. UUStation 安裝

將zip檔解壓縮完會有這三個icon，先執行「UUStation-3.1.0.37」。



2. 編輯 user1

回到解壓縮圖示點選「user1」按右鍵編輯。



② 將localhost改成publisher的UUID

③ 帳號密碼改成你在publisher上建立要給使用者使用的帳號

④ 編輯成功後「儲存」並關閉式窗。


3. 執行 user1

雙擊執行「user1」，完成後會出現「Command execution completed.」訊息。



```
C:\WINDOWS\system32\cmd.exe
C:\Documents and Settings\ivy\桌面>echo off
Command execution completed.
Publisher exists. Failed to add publisher!
UUStation is installed. Press any key to continue
請按任意鍵繼續 . . . =
```

執行成功後，即可得到一個你在publisher上所發布的IP，後即可使用UURemoteStation。



```
C:\WINDOWS\system32\cmd.exe
Description . . . . . : NIVIDIA nForce Networking Controller
Physical Address . . . . . : 00-1D-92-99-70-12
Dhcp Enabled . . . . . : No
IP Address . . . . . : 192.168.1.21
Subnet Mask . . . . . : 255.255.255.0
Default Gateway . . . . . : 192.168.1.254
DNS Servers . . . . . : 168.95.1.1

Ethernet adapter {0609B557-5408-4770-BADC-7F7D10107B1B}:

    Connection-specific DNS Suffix . :
    Description . . . . . : e-Caring Network Service - Packet Scheduling Miniport
    Physical Address . . . . . : 00-E0-4C-3C-7B-00
    Dhcp Enabled . . . . . : Yes
    Autoconfiguration Enabled . . . . . : Yes
    IP Address . . . . . : 172.25.52.82
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . :
    DHCP Server . . . . . : 172.25.52.83
    DNS Servers . . . . . : 172.25.1.100
    Lease Obtained . . . . . : 2010年8月13日 下午 05:14:13
    Lease Expires . . . . . : 2010年8月14日 上午 05:14:13

C:\Documents and Settings\ivy>
```